

# CISCO Secure Endpoint - Secure Endpoint API

## Authentication

The Secure Endpoint API requires access via an authenticated and authorized account. Only authorized accounts are able to submit requests to API operations. All operations must communicate over a secure HTTPS connection.

To authenticate and access the Secure Endpoint API, perform the following:

### **1. Integrate Secure Endpoint with Cisco XDR or Secure Client Cloud Management.**

- Navigate to the Secure Endpoint console.
- Click the Integrate Now button on the Secure Endpoint Dashboard.
- This enables the integration between Secure Endpoint and Cisco XDR or Secure Client Cloud Management.

Integrate xdr :

- Navigate to the Cisco XDR or Secure Client Cloud Management console and verify the integration.
- Enable the Integration (Cisco XDR only)
- Navigate to Administration -> Integrations, then click + Enable
- Enable Secure Endpoint

### **2. Register the API Client.**

- From within either Cisco XDR or Secure Client Cloud Management
- Navigate to Administration -> API Clients.
- On the API Clients page, click the Generate API Client button to open the Add New Client form.
  - add new client form
- Enter a Client Name and select a Scope.
  - Note: The Secure Endpoint API will work with any of the selected Scopes.
  - The API Client will have the same permissions within Secure Endpoint as the creator of the API Client.
- Optionally, enter a Description and click Add New Client.

- The Client Id and Client Password are generated and will appear on the Add New Client form. api credential form
- Secure the Client ID and Client Password before closing the window. Copy and paste it properly.

### 3. Generate an API Access Token.

## Method 1: Linux

Use the following OAuth2 token API to generate an API access token:

North America	<a href="https://visibility.amp.cisco.com/iroh/oauth2/token">https://visibility.amp.cisco.com/iroh/oauth2/token</a>
Asia Pacific, Japan, and China	<a href="https://visibility.apjc.amp.cisco.com/iroh/oauth2/token">https://visibility.apjc.amp.cisco.com/iroh/oauth2/token</a>
Europe	<a href="https://visibility.eu.amp.cisco.com/iroh/oauth2/token">https://visibility.eu.amp.cisco.com/iroh/oauth2/token</a>

The Client-Id and Client-Password (Client-Secret per OAuth2) generated in the previous step are required to call the token endpoint.

Get an Access Token via the Token API:

```
# Read in the client_id and client_secret if they are not already set.
[ -z "$client_id" ] && read -p "client_id: " client_id
[ -z "$client_secret" ] && read -p "client_secret: " client_secret

# Call the token endpoint and store the result in a variable.
result=$(curl -s 'https://visibility.eu.amp.cisco.com/iroh/oauth2/token' \
  --user "${client_id}:${client_secret}" \
  --header 'Content-Type: application/x-www-form-urlencoded' \
  --header 'Accept: application/json' \
  -d 'grant_type=client_credentials')

# Extract the access_token from the result.
export BEARER_TOKEN=$(echo "$result" | jq -r .access_token)

# Print the result.
[ -x "$(command -v jq)" ] && echo "$result" | jq . || echo "$result"
```

Response:

```
{
  "access_token": "eyJhbGciOi...",
  "token_type": "bearer",
  "expires_in": 600,
  "scope": "enrich:read casebook inspect:read"
}
```

#### 4. Generate Secure Endpoint API Access Token.

Use the following access token endpoint to generate a Secure Endpoint API access token:

North America	<a href="https://api.amp.cisco.com/v3/access_tokens">https://api.amp.cisco.com/v3/access_tokens</a>
Asia Pacific, Japan, and China	<a href="https://api.apjc.amp.cisco.com/v3/access_tokens">https://api.apjc.amp.cisco.com/v3/access_tokens</a>
Europe	<a href="https://api.eu.amp.cisco.com/v3/access_tokens">https://api.eu.amp.cisco.com/v3/access_tokens</a>

The API access token generated in previous step is required to call the token endpoint.

Get and Access Token from the Secure Endpoint Token API:

```
# Call the Secure Endpoint token endpoint and store the result in a variable.
result=$(curl -s 'https://api.amp.cisco.com/v3/access_tokens' \
  --header 'Content-Type: application/x-www-form-urlencoded' \
  --header 'Accept: application/json' \
  --header "Authorization: Bearer $BEARER_TOKEN" \
  -d 'grant_type=client_credentials')

# Extract the access_token from the result.
export BEARER_TOKEN=$(echo "$result" | jq -r .access_token)

# Print the result.
[ -x "$(command -v jq)" ] && echo "$result" | jq . || echo "$result"
```

Response:

```
{
  "access_token": "eyJhbGciOi..."
}
```

## 5. Access Secure Endpoint API.

The token generated in previous step is used to access the Secure Endpoint APIs.

Request:

```
# Call the Secure Endpoint API and store the result in a variable.
result=$(curl -s 'https://api.amp.cisco.com/v3/organizations?size=10' \
  --header "Authorization: Bearer ${BEARER_TOKEN}")

# Print the result.
[ -x "$(command -v jq)" ] && echo "$result" | jq . || echo "$result"
```

Response:

```
{
  "meta": {
    "start": 0,
    "size": 10,
    "total": 2
  },
  "data": [
    {
      "name": "Example Organization #1",
      "organizationIdentifier": "4baascfeaofqpxidpinxtt5l"
    },
    {
      "name": "Example Organization #2",
      "organizationIdentifier": "nxtf3phj4w0z41pim3vqarzk"
    }
  ]
}
```

## Method 2: Windows

### 1. Set Client ID and Client Secret

The script reads `client_id` and `client_secret` from the user if not set and uses them to request an OAuth2 token.

```

@echo off
REM Check if client_id and client_secret are set
if "%client_id%"==" " set /p client_id="Enter client_id: "
if "%client_secret%"==" " set /p client_secret="Enter client_secret: "

REM Call the OAuth2 token endpoint
curl -s -u "%client_id%:%client_secret%" ^
  -H "Content-Type: application/x-www-form-urlencoded" ^
  -H "Accept: application/json" ^
  -d "grant_type=client_credentials" ^
  https://visibility.amp.cisco.com/iroh/oauth2/token > token.json

REM Extract the access_token using jq (ensure jq is installed)
for /f "delims=" %%A in ('jq -r ".access_token" token.json') do set BEARER_TOKEN=%%A

REM Output the token
echo OAuth2 Access Token: %BEARER_TOKEN%

```

## 2. Generate Secure Endpoint API Access Token

Use the token from the previous step to generate an API access token for Secure Endpoint.

```

@echo off
REM Call the Secure Endpoint token endpoint
curl -s -X POST ^
  -H "Content-Type: application/x-www-form-urlencoded" ^
  -H "Accept: application/json" ^
  -H "Authorization: Bearer %BEARER_TOKEN%" ^
  -d "grant_type=client_credentials" ^
  https://api.amp.cisco.com/v3/access_tokens > endpoint_token.json

REM Extract the access_token using jq (ensure jq is installed)
for /f "delims=" %%A in ('jq -r ".access_token" endpoint_token.json') do set SECURE_ENDPOINT_TOKEN=%%A

REM Output the Secure Endpoint API token
echo Secure Endpoint API Access Token: %SECURE_ENDPOINT_TOKEN%

```

## 3. Access the Secure Endpoint API

```

@echo off
REM Call the Secure Endpoint API
curl -s -X GET ^
  -H "Authorization: Bearer %SECURE_ENDPOINT_TOKEN%" ^
  https://api.amp.cisco.com/v3/organizations?size=10 > organizations.json

REM Output the API response
echo Secure Endpoint API Response:
type organizations.json

```

Key Notes:

## Prerequisites:

- Install curl (default on Windows 10/11 or available via Chocolatey).
- Install jq for JSON parsing (available via jq).
- Save and Run:
- Save the script as a .bat file (e.g., get\_token.bat).
- Run the script in Command Prompt or PowerShell.
- Replace Region URLs:
- Use the appropriate region URL in the curl commands (e.g., North America, APJC, or Europe).

Source: <https://developer.cisco.com/docs/secure-endpoint/authentication/#3-generate-an-api-access-token>

---

Revision #6

Created 17 January 2025 05:42:55 by Richmond Abella

Updated 27 February 2025 09:31:16 by Richmond Abella